Troubleshooting

This page provides troubleshooting steps for dealing with errors and other issues that could possibly occur when working with or setting up the various parts of the motoman_driver (/motoman_driver) package. The *Solution* subsections list steps to resolve the issues.

If you have a specific issue that is not listed on this page or the provided solution does not seem to work, please contact the developers by sending an email to the ROS-Industrial (https://groups.google.com/forum/?fromgroups#!forum/swri-ros-pkg-dev) mailing list (direct mail: ROS-Industrial (mailto:swri-ros-pkg-dev@googlegroups.com)).

1. Troubleshooting 1. Installation 1. ERROR 3200: NOP or END instruction not found 2. Runtime 1. Alarm: 8001[0] 2. Alarm: 8003[100 - 111] 3. Alarm: 8003[1] 4. Alarm: 8003[2] 5. Alarm: 8003[3] 6. Alarm: 8003[4] 7. Alarm: 8003[5] 8. Alarm: 8003[6] 9. Alarm: 8003[7] 10. Alarm: 8003[8]

1. Installation

1.1 ERROR 3200: NOP or END instruction not found

The robot controller requires all files use Windows-style end-of-line terminator. This is <carriage return><line feed>. Many common text editors in the Linux environment will automatically standardize all EOL terminators to be Unix-style; this removes the <carriage return>, resulting in the error message.

Solution: Open this job file in a text editor that allows you to use Windows-style EOL (<0xD><0xA> or <CR><LF>) or, given that the job is relatively small, manually recreate the job using the programming pendant. Another alternative is to copy the .jbi and .dat files under Windows.

2. Runtime

2.1 Alarm: 8001[0]

Example:

```
ALARM 8001
WARNING: Too many groups for ROS
[0]
```

Solution: The MotoROS driver can support up to 4 control-groups on FS100, DX200, and YRC1000 controllers. The DX100 can support up to 2 control-groups. This alarm indicates that your controller is setup with more groups than what is supported. This is a warning to notify you that the additional groups will not be controlled by the MotoROS driver. They will remain stationary during operation.

2.2 Alarm: 8003[100 - 111]

Example:

```
ALARM 8003

MotoROS: Controller cfg invalid
[100]
```

Solution: Your robot controller requires internal configuration changes to support the MotoROS driver.

For DX100 and FS100: Please contact your local Yaskawa Motoman office to order the MotoROS runtime. In North/South America, the part numbers for this configuration are 180014-1 (DX100) and 180015-1 (FS100). In Europe, the part number for this configuration is 171403

For DX200 and YRC1000: Ensure your controller is updated to at least DN2.21.00-00 or YAS1.11.00-00 system software. If your controller is below this, please contact Yaskawa Motoman for assistance with upgrading the controller. Then boot the controller into Maintenance mode by holding {Main Menu} on the keypad. Touch [System Info] > [Security] and upgrade to MANAGEMENT security level. Touch [System Info] > [Setup] > select OPTION FUNCTION. Cursor down to MOTOMAN DRIVER and set this to USED. Then reboot your robot controller.

2.3 Alarm: 8003[1]

Example:

```
ALARM 8003
MotoROS Cfg: Set RS000=2
[1]
```

Solution: An internal parameter is not set properly in the robot controller. Touch [System Info] > [Security] and upgrade to MANAGEMENT security level. Then touch [Parameter] > [RS] and set the value of RS000 = 2. Then reboot your robot controller.

2.4 Alarm: 8003[2]

Example:

```
ALARM 8003
MotoROS Cfg: Set S2C541=0
[2]
```

Solution: An internal parameter is not set properly in the robot controller. Touch [System Info] > [Security] and upgrade to MANAGEMENT security level. Then touch [Parameter] > [S2C] and set the value of S2C541 = 0. Then reboot your robot controller.

2.5 Alarm: 8003[3]

Example:

```
ALARM 8003
MotoROS Cfg: Set S2C542=0
[3]
```

Solution: An internal parameter is not set properly in the robot controller. Touch [System Info] > [Security] and upgrade to MANAGEMENT security level. Then touch [Parameter] > [S2C] and set the value of S2C542 = 0. Then reboot your robot controller.

2.6 Alarm: 8003[4]

Example:

```
ALARM 8003
MotoROS Cfg: Set S2C1100=1
[4]
```

Solution: An internal parameter is not set properly in the robot controller. Touch [System Info] > [Security] and upgrade to MANAGEMENT security level. Then touch [Parameter] > [S2C] and set the value of S2C1100 = 1. Then reboot your robot controller.

2.7 Alarm: 8003[5]

Example:

```
ALARM 8003
MotoROS Cfg: Set S2C1103=2
[5]
```

Solution: An internal parameter is not set properly in the robot controller. Touch [System Info] > [Security] and upgrade to MANAGEMENT security level. Then touch [Parameter] > [S2C] and set the value of S2C1103 = 2. Then reboot your robot controller.

2.8 Alarm: 8003[6]

Example:

```
ALARM 8003
MotoROS Cfg: Set S2C1117=1
[6]
```

Solution: An internal parameter is not set properly in the robot controller. Touch [System Info] > [Security] and upgrade to MANAGEMENT security level. Then touch [Parameter] > [S2C] and set the value of S2C1117 = 1. Then reboot your robot controller.

2.9 Alarm: 8003[7]

Example:

```
ALARM 8003
MotoROS Cfg: Set S2C1119=0 or 2
[7]
```

Solution: An internal parameter is not set properly in the robot controller. Touch [System Info] > [Security] and upgrade to MANAGEMENT security level. Then touch [Parameter] > [S2C] and set the value of S2C1119. A value of 2 will enable the telnet option to see any output messages from the MotoROS driver. A value of 0 will disable the telnet option. Reboot your robot controller after changing this parameter.

2.10 Alarm: 8003[8]

Example:

```
ALARM 8003

MotoROS not compatible with PFL
[8]
```

Solution: The MotoROS driver is not compatible with the human-collaborative features of the HC robots. Reboot the robot controller while holding {Main Menu} on the keypad to enter Maintenance mode. Touch [System Info] > [Security] and upgrade to MANAGEMENT security level. Then touch [MotoPlus (/MotoPlus) Apl] > [Delete]. Select PLF.out and press {Enter} to confirm removal of the PFL driver.

Except where otherwise noted, the ROS wiki is licensed under the Wiki: motoman_driver/Troubleshooting (last edited 2017-04-18 14:40:29 by TedMiller (/TedMiller))

Creative Commons Attribution 3.0

(http://creativecommons.org/licenses/by/3.0/) | Find us on Google+(https://plus.google.com/113789706402978299308)

Brought to you by: Open Source Robotics Foundation

(http://www.osrfoundation.org)